


apulSoft apQualizr2 v2.1.1 Manual

modular equalizer audio plugin
(VST/VST3/AU/AAX)

©2015-2017 by apulSoft
<http://www.apulsoft.ch>

VST plugin technology by Steinberg.
AU plugin Technology by Apple.
AAX plugin Technology by Avid.
Manual written with \LaTeX on August 4, 2017

Introduction



apuSoft apQualizr2 is an audio plugin based on a multiband equalizer layered on top of a frequency analyzer with elements of a modular effects system. It features graphical editing of top quality low latency filters and modular modulation of various filter parameters. It can be used for all standard eq applications and can produce many modulation and dynamics effects thanks to the dynamics and lfo modules included.

apQualizr2's filters are based on a unique method to match ideal frequency response curves over the entire frequency spectrum while maintaining minimal latency. Applicable filter types have adjustable steepness (adjustable number of poles) and can be individually switched to Mid-Side processing.

Contents

1	End User License Agreement	4
2	System Requirements	5
3	Installation	5
4	Overview	6
5	Top Bar	7
5.1	Preset Section/Undo/Redo	7
5.2	License	7
6	Frequency Analyzer/Frequency Response Curve Display	8
6.1	Filter Band Creation	9
6.2	Filter Types	9
6.3	Editing Filters	10
6.4	Piano Ruler	11
7	Module Tray	11
7.1	Module Interface	11
7.2	Cables	12
8	Module Types	12
8.1	Analyzer	12
8.2	Output	13
8.3	Filter Band	14
8.4	LFO	14
8.5	Dynamics	15
8.6	Signal Scope	16
8.7	Mix	17
8.8	Split	17
8.9	Knobs	17
9	Plugin Settings & Information Page	18
10	Init and Factory Presets	19
10.1	Init Preset	19
10.2	EQ Anatomy Presets by Simon Millward	19
11	Unlocking the Full Version of apQualizr2	20
12	Frequently Asked Questions (FAQ)	21
13	Changelog	22

1 End User License Agreement

END-USER LICENSE AGREEMENT FOR apulSoft

This apulSoft End-User License Agreement ("EULA") is a legal agreement between you (either an individual or a single entity) and apulSoft for the software accompanying this EULA, which includes computer software and electronic documentation ("SOFTWARE PRODUCT" or "SOFTWARE"). By exercising your rights to make and use copies of the SOFTWARE PRODUCT, you agree to be bound by the terms of this EULA. If you do not agree to the terms of this EULA, you may not use the SOFTWARE PRODUCT.

DISCLAIMER OF WARRANTY

This product is provided on an "AS IS" basis, without warranty of any kind, expressed or implied, including any warranties of fitness for a particular purpose. The authors shall not be liable for damages of any kind. Use of this software indicates you agree to this.

SOFTWARE PRODUCT LICENSE

The SOFTWARE PRODUCT is protected by copyright laws and international copyright treaties, as well as other intellectual property laws and treaties. The SOFTWARE PRODUCT is licensed, not sold.

GRANT OF LICENSE

Installation and Use: You may install and use copies of the SOFTWARE PRODUCT on all computers you own. **Reproduction and Distribution:** You may not reproduce or distribute the SOFTWARE PRODUCT except to make backup copies, or to install as provided for above.

DESCRIPTION OF OTHER RIGHTS AND LIMITATIONS

Limitations on Reverse Engineering, Decompilation and Disassembly: You may not reverse engineer, decompile, or disassemble this SOFTWARE PRODUCT. **Software Transfer:** You may permanently transfer all of your rights under this EULA, provided you retain no copies, you transfer all of the SOFTWARE PRODUCT, and the recipient agrees to the terms of this EULA. **Termination:** Without prejudice to any other rights, apulSoft may terminate this EULA if you fail to comply with the terms and conditions of this EULA. In such event, you must destroy all copies of the SOFTWARE PRODUCT and all of its component parts.

COPYRIGHT

All title and copyrights in and to the SOFTWARE PRODUCT (including any images and text) incorporated into the SOFTWARE PRODUCT, the accompanying printed materials, and any copies of the SOFTWARE PRODUCT are owned by apulSoft or its suppliers.


2 System Requirements

- A Mac with an Intel CPU running OS X 10.6.8 or newer or a Windows PC with a SSE2 capable CPU running windows XP or newer.
- A host application that can load VST, VST3, AudioUnits or AAX plugins running in 32-bit or 64-bit mode.
- Pro Tools (AAX): The minimum required version is 10.3.5.
- An application to view pdf files to read this manual.

3 Installation

- Mac OS X
 - Quit all plugin host applications.
 - Double-click **apqualizr2-mac-(..).pkg**. In case Mac OS X tells you the software is coming from an unidentified developer with no option to open it, right-click on the downloaded file and choose "Open" to get a dialog with the option to open it.
 - Follow the standard OSX installation procedure.
 - Open a host and create an instance of apQualizr2 in a plugin slot.
 - The apQualizr2 GUI will show a welcome screen with the options to run the plugin in demo mode or to buy or enter license information.
- Windows
 - Quit all plugin host applications.
 - Double-click the **apqualizr2-installer-win-(..).exe** to start the installation. On newer versions of windows it may be necessary to confirm the launch because of user access management.
 - Follow the installation procedure. During the install you have the option to set the path to the apQualizr2 data folder. That is where settings, presets and the manual will be installed.
 - If VST2 versions are installed, the installer will provide the option to select destination folders for VST2 plugins for both 32-bit and 64-bit.
 - Open a host and create an instance of apQualizr2 in a plugin slot.
 - The apQualizr2 GUI will show a welcome screen with the options to run the plugin in demo mode or to buy or enter license information.

4 Overview



The apQualizr2 user interface has three main parts. On top is a status bar with the settings button, plugin title, preset selection, undo/redo buttons and license information.

The large area below is where the analyzer graphs are shown and frequency response curves are shown and adjusted using handles.

At the bottom is the module tray. Between the two built-in analyzer and output modules, a module is shown for each created filter band and optionally more modules can be created by the user to modulate filter band settings. The modules can be moved using drag and drop and module in- and outputs allow the user to create cables to create arbitrary module graphs.

Most of the controls on the GUI can be dragged with the mouse to change values.

- If the **[Shift]** key is held down the values with knobs will snap to predefined markers at round values. On the frequency graph, holding **[Shift]** locks dragging to the frequency or gain axis.
- Holding **[Ctrl]** switches the dragging to a mouse-velocity based mode allowing for very tiny changes for slow mouse movements.
- Clicking a control while holding **[Alt]** sets the value to the default value for knobs and labels. Holding **[Alt]** while the mouse is above the main graph enables the band-pass listening mode where an additional variable bandwidth bandpass filter is applied to the output to quickly listen to specific frequencies only.
- Most of the value-based controls can be double-clicked to open a popup value editor to be used with the keyboard.

5 Top Bar



On this grey bar at the top of the apQualizr2 user are the settings button (with the gear icon) and the apQualizr2 title which both open the plugin settings dialog, the preset section and the license section on the very right.

5.1 Preset Section/Undo/Redo

The white box shows the label of the current preset and can be clicked to edit the label. The "i" button on the left opens the preset description popup that can also be used to edit the description.

On the right side are up/down arrow buttons to cycle through presets inside the same folder as the currently loaded one. The rightmost button opens the preset menu. It lists all available presets with folders as they are organized on disk. Below the presets the following entries are available:

Save Current Preset.. The current state of the plugin is added to the preset menu. In the prompt that pops up, the preset name can be edited and folder paths can be added which automatically creates folders on disk if necessary. Presets in the menu can be overwritten by using the same name/path.

Import Preset.. Load a preset from a .apq2preset file anywhere on the local filesystem.

Export Current Preset.. Store the current state of the plugin as a .apq2preset to any location on your local filesystem.

Manage Presets Folder in Finder/Windows Explorer.. This opens the filesystem folder that contains the presets shown in the menu. The usual file operations can be used to restructure this folder and therefore restructure the presets menu.

To the right of the white preset box are the **Undo** and the **Redo** button. These undo and redo that last actions when clicked. apQualizr2 currently support unlimited undo and redo.

Note: Saving and importing of presets is only available in the full version of apQualizr2.

5.2 License


The look of the license section changes depending on your license status. In demo mode there are two buttons:

Buy apQualizr2.. Opens the system default browser on the apQualizr2 webpage where it is possible to buy an apulSoft apQualizr2 license.

Enter Serial.. Once you have the ID/serial information, click this button to enter your information and unlock the full version of the plugin.

If the full version of the plugin was successfully unlocked, then the license section will display the license ID.

6 Frequency Analyzer/Frequency Response Curve Display



This main display of apQualizr2 is where frequency graphs are shown, filters are created and edited by dragging on their handles.

On the left and bottom side of the graph there are range sliders which can be used to adjust the viewed frequency range as well as the displayed dB range of the analyzer graph.

On the top right the \pm dB range of the filter curve is shown and can be adjusted by a popup menu. If a filter handle is dragged near the top or bottom border, the filter range auto extends. If filter handles are moved towards the left or right borders, the frequency range automatically scrolls.

On the bottom bar there are a number of additional buttons.

r Reset the graph viewport area to the values defined in your **Init** preset.

Module tray toggle If it's on, the module tray is shown, if not it is hidden and almost the full plugin interface is used for the graph display. If you just want to do classic equalization, the module bar might not be necessary.

Piano ruler toggle Controls the visibility of the piano ruler display on the bottom of the graph.

Del Delete the currently selected filters and/or modules. The same thing can be achieved by pressing `Delete` or `Backspace` on the keyboard.

Dup button duplicates the currently selected filters and/or modules with identical settings. For filters this means two filter main handles lie on top of each other after this operation.

6.1 Filter Band Creation

Clicking on empty space on the graph brings up the filter creation popup (if nothing is selected). A list of the available filter types is shown. Clicking on one of the list entries creates a new filter of the selected type at the clicked frequency and gain location.

Right-clicking brings up the chooser as well, but regardless of selection state. It also immediately shows the menu, so Right-click + drag can be used to create a new typed filter band with just one mouse gesture.

Double-clicking on empty space on the graph creates a new peak EQ filter band without showing the chooser.

6.2 Filter Types

Peak EQ Boosts/attenuates the frequency band around a center frequency. It has an adjustable bandwidth in octaves that is defined by half the gain-value. Higher pole versions lead to a flat gain plateau around the center frequency.

Band Stop Cuts out a band of frequencies completely. Bandwidth defines the -3dB points. This type has no gain parameter.

Lowpass Cuts frequencies above a cutoff value and lets low frequencies through. The gain value adds resonance to the lowpass which boosts/attenuates frequencies around the cutoff frequency.

Highpass Cuts frequencies below a cutoff value and lets high frequencies through. The gain value adds resonance to the highpass which boosts/attenuates frequencies around the cutoff frequency.

Bandpass High and low frequencies outside the bandwidth area are removed from the signal and gain is applied. The bandwidth spans between the two -3dB points.

Lowshelf Lowshelf filters boost or cut low frequencies by the amount set up by the gain parameter. There is a transition area which width depends on the number of poles used. The frequency parameter defines the middle of the transition region where half the gain is applied.

Highshelf Highshelf filters boost or cut high frequencies by the amount set up by the gain parameter. There is a transition area which width depends on the number of poles used. The frequency parameter defines the middle of the transition region where half the gain is applied.

Comb The comb filter produces many evenly spaced frequency spikes at the same time. The frequency and gain parameter set up the lowest spike. As the spikes are evenly spaced frequency-wise they appear to get more and more dense towards higher frequencies as the frequency graph (and human hearing) work logarithmically. Technically the comb filter is implemented as a short delay with feedback.

6.3 Editing Filters

Filter frequency and gain can be changed by dragging the main filter handle on the graph. Clicking or dragging a handle will automatically select the filter band.


Selected filters show additional handles depending on the capabilities of the filter type. Most filters support changing their steepness/poles count. In that case a rotary handle is displayed around the main filter handle which can be used to change the pole count by dragging up/down or left/right.

Filter types with a bandwidth parameter show a green area that show the set bandwidth. Dragging the two thin lines on the left and the right border with the mouse changes the bandwidth of the filter.

Various mouse modifiers are available during editing:

Mouse drag on empty area	Rubber-band selection of multiple filter bands.
Shift -Click	Select multiple filters to edit them together.
Ctrl - A	Select all filter bands at once.
Ctrl -Click	Bypass/Reenable the selected bands.
Double-Click	Bypass/Reenable the selected bands.
Alt	Holding Alt switches to band-pass listening mode which applies a variable bandwidth band pass filter to the plugin output. Use Alt -mouse wheel on empty space to quickly change the bandwidth.
Right-Drag	Dragging a filter handle with the right mouse button switches to bandwidth adjusting mode.
Ctrl -Drag	Switch to velocity-based value dragging. Slow movements allow for tiny adjustments.
Shift -Drag	Lock dragging to the frequency or gain axis depending on which one has the larger change at the time of pressing Shift
B	Holding B while dragging a filter handle switches to bandwidth adjusting mode.
Mouse Wheel	Turning the mouse wheel while the mouse pointer hovers over a filter handle adjusts the bandwidth for filter types with bandwidth property and the number of poles for other types. While holding Alt the mouse wheel adjusts the bandwidth of the frequency band solo filter.

6.4 Piano Ruler



If the the piano ruler toggle button left of the bottom scroll bar of the graph view is enabled, a piano ruler is displayed at the bottom of the display. Using the preferences setting about A4 tuning, the position of each musical note is calculated so the keys match the frequency position of their fundamental note. The piano ruler displays an orange handle for each filter center frequency. If these handles are dragged, the frequencies are quantized to musical pitches.

7 Module Tray

The module tray is shown as the bottom section of the user interface if the module tray toggle button at the bottom left of the graph display is enabled.

The module tray always shows the analyzer module at the very left and the output module on the very right. In between a module is displayed for each filter created as well as all the additional modulation modules created by the user.

The order of the modules can be changed by dragging and dropping modules.

New modulation modules can be added by clicking on the large plus button. A popup menu with the available module types is displayed to choose what new module to create. Modules can also be created by right clicking unconnected module inputs and choosing the module to create in the input context menu.

7.1 Module Interface

Each module has a title bar with its name and a module menu (for user-created modules). The module name for all user created modules can be edited by double-clicking on it. If the name of a filter module is changed, it will be displayed near the filter handle on the graph view above.

The module menu allows to duplicate and delete modules. Some modules feature additional entries in the plugin menu described in the module types section below.

Below the title bar is the individual interface of each module. Dragging on the space between controls allows to reorder modules.

Custom module inputs are displayed on the left side of modules and custom outputs on the right side as darker rounded areas. Some modules have knobs with additional modulation inputs on their top left corner. These look like dark circles. Dragging the mouse on any of the inputs/outputs creates a new cable. Right-clicking an unconnected input/output brings out options to directly create and connect new modules.

7.2 Cables

Clicking and dragging on custom module input and outputs allows to create modulation cables. Right-clicking a cable brings up a cable popup menu where the cable color can be changed, the cable can be replaced by a module or the cable can be deleted.

Any output can be connected to any input as long as there is no feedback loop.

8 Module Types

8.1 Analyzer

The analyzer module is always the leftmost module in the modules tray and controls various analyzer-related settings.

In & Out These two toggle buttons enable the two analyzer stages which are inserted at different points in the signal path. **In** enables the input analyzer right at the plugin input before any processing is applied by apQualizr2. **Out** enables the output analyzer which is placed just before the plugin output after all the processing has happened including output gain and output clipping.

Res This setting defines the number of samples used as FFT block size. This is directly proportional to the displayed frequency resolution. The higher the resolution, the more detailed the frequency graph gets. However at the same time the larger blocks mean the display reacts slower to changes and the transients get smoothed more. Higher resolutions also require more processing power.


Decay The speed at which the frequency graph moves downward. **Frz** means all freqs stay at their maxima.

Tilt This setting optionally applies a tilt to the graphical output. At the **0 dB/Oct** setting the display is mathematically accurate and white noise gets displayed as a horizontal line. Music tends to fall off towards higher frequencies and the **3 dB** and **4.5 dB** settings allow to compensate for that. Common sound then appears more like a horizontally balanced graph.

Note: Tilt is only applied to the analyzer graphs, not the filter frequency curves!

Match Delay This toggle switch enables an internal delay which is set to half the fft block size. At the same time this amount of delay time is reported to the host application as plugin latency. The intention is to better align the visual fft graph with the audible sound. To make it work, the host application needs to support plugin latency compensation. **Notes:** Many hosts do not support changing latencies while the audio is running. In this case the host transport needs to be restarted for things to work. This setting is definitely not recommended for live usage!

Stereo Mode This popup menu is only available if apQualizr2 is used on a stereo channel and shows the various stereo view modes for displaying the frequency analyzers.



Left & Right Two analyzer curves are displayed for each analyzer. A green tint is used for the left channel, a red tint for the right channel.

Left-Right Mix For each frequency value, the left and right channels gains are added and multiplied by 0.5.

Left-Right Max For each frequency value, the maximum gain of the left and right channels is used.

Left only Only the left channels curve is displayed.

Right only Only the right channel curve is displayed.

Mid & Side The input signal is converted to a mid and a side signal. The side signal is displayed as a black line, while the mid signal is shown as a yellow area.

Mid only Show the mid channel only. This is the same as Left-Right Mix.

Side only Show the side channel only.

8.2 Output


The output module is always the rightmost module in the tray and is always present. It controls the master gain and an optional output clipper. The master gain has a modulation input. The clipper has four modes:

Off No clipping is applied. **Note:** If extreme filter settings are used, very loud signals can occur!

Hard Any value above 1.0 (0dB) is hard clipped at 1.0 (0dB). This produces quite harsh digital distortion if high values happen.

Soft Soft clipping also makes sure no sample goes over 1.0, but values are gradually softened over 12dB.

Asym Asymmetrical soft clipping lowers levels for the top 9dB of the positive signal side and for the top 15dB of the negative signal side.




The lower part of the output module is a graphical display that shows how much clipping has been applied over time. For stereo instances, it always shows the maximum clipping applied.

8.3 Filter Band

For each filter band created on the main graph view, a filter band module is automatically created. It allows to edit filter parameters and add modulation cables to some of them. Depending on filter type, different parameters will show up. More information about filter types is available in the filter type description chapter.

The filter module menu on top right has the additional option to change filter type while maintaining filter parameters.

On bottom right, the filter module has a signal output. If a cable is connected to this aux output, the filter is removed from normal processing and directly processes the input signal and then feeds the result to the aux output. This way modulation can be based on just a frequency band of the input (for instances in multi-band compressors).



8.4 LFO

The LFO (Low frequency oscillator) module generates various repeating signals. In **Free** mode, the LFO generates its own tempo based on a Hertz value and in **Sync** mode the LFO can sync to the host beat tempo. In that case, the frequency knob adjusts the ratio to the host beat.

Note: not all hosts supply beat information.

The LFO module supports these waveform types:


Off The module is turned off and outputs a stream of 0.

Sine A mathematically correct sine curve.

Triangle A triangle wave.

Square A square wave switching between amp and -amp (defined by the **Amp** knob).

Random Hold At the beginning of each oscillator cycle, a random value is generated and then held for the cycle duration.



The four main controls of the LFO module are controlled by knobs and all can be modulated by connecting a cable to the modulation inputs next to the knobs.

The **Freq** knob adjusts the LFO frequency or its ratio to the host beat tempo.

The **Smooth** button defines the amount of smoothing applied to the LFO output. The smoothing is always relative to the oscillator frequency so the waveform shape does not change if the frequency changes.

The **Phase** setting offsets the waveform by a % value. A 50% phase setting means the waveform starts at its middle. Multiple LFOs with the same settings usually run in sync and using phase fixed ratios can be obtained. **Note:** If the frequency knob is adjusted, LFOs might lose sync and only restarting host playback will make them sync again.


The **Amp** knob sets the LFOs amplitude.

On the bottom right is the one output of the module to be connected to modulation targets with a cable.

8.5 Dynamics

The dynamics module converts an audio signal coming from the cable connected to the input on the left into a dynamics signal that can be used to modulate parameters on other modules. It can be an envelope follower, a peak hold detector, a transient detector or a complete compressor control circuit.

There are two meters on this module. The one on the left shows the dB level of the incoming signal. Layered onto that is the threshold value showing the knee area as a gray bar. The threshold can be adjusted by dragging it with the mouse. The right one shows the output signal. Depending on where the output cable is connected to, different value units are displayed.



On the module title bar one of three main modes can be selected. **Peak** is the peak hold mode to capture fast transients in the audio. It means the maximum sample values are held for the time set up by the **Size** parameter. **RMS** stands for "Root Mean Square". This means for the duration of the **Size** parameter, squared samples values are summed and the sum is divided by the size. RMS mode is good for slower material and is a way to measure the energy contained in the signal. **Trans** mode uses a special algorithm to detect transients in the audio. Transients are steep rises of energy in the signal. In this mode the **Size** parameter defines the scale of transients to capture. The transient mode only captures transients above the threshold.

The dynamics module has one input and one output. If nothing is connected to the input the dynamics module connects by itself to the plugin input. Once something else is connected to the input (such as a filter band aux output), the connection to input is removed.

In the center of the dynamics module, multiple parameters can be adjusted:

Thresh The threshold value in dB. This is also shown as a line on top of the input level meter. It

determines the level above which dynamics processing starts.

Size The size parameter works differently depending on the dynamics module mode (set on the module title bar). In **Peak** mode, it is the duration, for which maximum samples are held. In **RMS** and **Trans** modes it is the size of the processing window, the duration of audio that is considered for each output value.

Ahead Stands for Lookahead. This is the time the dynamics module “looks into the future” during the processing so modulation can occur before transients have already happened. If lookahead is set above zero, the dynamics module will introduce latency in the signal chain. Hosts with plugin delay compensation can make up for that by sending audio earlier, but not all hosts support changing latencies while transport is running. To make sure, things are running in sync, restart the host transport.

Attack/Release The attack/release times of the built in envelope follower. These set the time the output signal takes to rise/fall by 10 dB and can be used to smoothen the output signal.

Knee The soft-knee control defines the area over which the dynamics processing gradually sets in in dB. 10 dB means dynamics processing begins 5 dB below the threshold and the full ratio/amp setting is reached 5 dB over the threshold. This value is shown as a grey area on top of the threshold meter/slider combo view.


Amp/Ratio The dynamics module has two ways of multiplying the output signal which can be switched below this knob. In **Amp** mode, the value above the threshold is taken and multiplied by the amplification value. In **Ratio** mode, the output signal is multiplied in a different way to become a gain reduction signal that can be used to drive the gain of filters or the master output to get compressor-like behaviour.

8.6 Signal Scope

The signal scope module can be used to visualize signals. It automatically picks up the signal unit if available and its view duration can be adjusted at the bottom.

The module just feeds the signal through and can therefore be placed between a modulation source and target.


To visualize the signal going through a cable, right-click the cable and choose “Insert Signal Scope”. If a scope module with cables connected on both sides is deleted, a shortcut cable is created.



8.7 Mix

The mix module allows to mix up to three signals together and multiply the result with an amplification factor (**Amp**) which can itself be modulated by a signal.


The multiplied sum is fed to the output on the bottom right corner.



8.8 Split


The split module outputs the input signal to three separate outputs. Each output can be amplified by an individual amp factor.

These factors each have modulation inputs.



8.9 Knobs

The knobs module provides two large knobs that can be used as a source for modulation. Both knobs can be renamed and output a smoothed stream of the knob value. The knobs module exposes the knob values as automatable parameters to the host. In combination with the Split and Mix modules, one knob can be used to automate multiple module parameters at once.



9 Plugin Settings & Information Page

The top section of the settings dialog shows some basic information about the plugin.

In the middle there are some global settings. These apply to all instances of apQualizr2. All instances using the same plugin format in the same host will update immediately, others update once the plugin is reloaded.

Show Tooltips when hovering If this is activated, orange rectangles with little hint texts will pop up if the mouse hovers in place over a control for a second.


Show freq/gain grid If this is toggled on, frequency and gain grid lines are drawn on the main apQualizr2 frequency/gain view.

A4 tuning If you use the piano ruler or enter note names to get specific frequencies, this setting is used to convert between (midi-based) note names and frequency values. The right side popup button shows some commonly used values or any number can be entered using the keyboard.

Freq-Solo Bandwidth Holding **[Alt]** while the mouse is above the main graphical display temporarily adds a bandpass filter to listen to a frequency band only while everything else keep working normally. This setting defines the bandwidth used for the filter and can also be adjusted using the mouse wheel while holding **[Alt]**.

GUI Scale Choose how large the plugin GUI should be drawn in %. The right-side popup features a few presets and it is also possible to just enter any value between 25 and 500. Some hosts might only display the plugin correctly at the new size once the plugin window is closed and reopened. In extreme cases, the host might need to be restarted.

GUI Redraw Rate The number of interface redraws per second. A slow computer might not be able to reach high rates. High refresh rates will only work well with small host audio buffer sizes.



GUI Color Scheme Switch between multiple color schemes for the interface. The menu will show all installed schemes and new ones can be added by the user by renaming and editing the existing scheme files. These are located in a folder called ColorSchemes next to the apQualizr2 presets folder. Use the **Manage in Finder/Explorer..** entry of the presets menu to navigate to the presets folder. The color schemes use an xml based format that can be edited in any text editor. More information can be found inside the **Bright.xml** file.

At the bottom of the preferences dialog there are four buttons:

apulSoft Homepage.. This opens <http://www.apulSoft.ch> in the default browser.

Open the Manual.. The apQualizr2 manual is opened in the default pdf viewer application.

Check for Updates.. This opens a special page on the apulSoft homepage and sends version information. The homepage checks the version against the latest release and provides links to downloads if newer versions are available.

Edit Serial/ID.. This button (re-)opens the serial information entry dialog. You can use it to enter, look up or edit your license information.

10 Init and Factory Presets

apQualizr2 installs a number of example presets by default. All factory presets include descriptions that are accessible by clicking the **i** button on the left side of the current preset name.

10.1 Init Preset

A special preset is the **Init** preset. The first time the plugin is opened it is auto-generated from the plugin's default values. Every time a new instance of apQualizr2 is created, the **Init** preset is loaded. This allows you to set up your personal default values by overwriting this preset once the plugin is in the desired default state. The "reset viewport" button in the bottom left corner of the main graph sets the visible ranges to the values defined in the **Init** preset.

10.2 EQ Anatomy Presets by Simon Millward

The EQ Anatomy presets indicate the key frequency bands where popular musical instruments may be boosted or cut. The effect of each band's boost or cut is indicated by a label. These presets may be used as a guide to create your own filtering curves on top, or each band in the curve may be individually switched on or off using the Bypass switch for each filter (use Ctrl-Click/Double-Click on the filter handles in the display).

The EQ Anatomy curves were created using typical instrument sounds in each category but may need tweaking to achieve the desired effect with your own sounds.

All EQ Anatomy presets created by:
Simon Millward

(as published in 'Fast Guide to Cubase 6')

II Unlocking the Full Version of apQualizr2

apQualizr2 Authorization

Unlock apQualizr2
Please enter your ID and serial number below.

ID:

Serial:

Once you bought an apQualizr2 license via ShareIt from the apulSoft homepage (which can be opened from the demo welcome screen or the demo plugin license interface section), use the **Enter ID/Serial..** buttons on either the demo welcome screen or on the bottom right of the demo license GUI section to open the license input dialog.

Just enter the ID/serial exactly as received and click **OK**.

In case the ID/serial is not accepted, check the following things:

- The serial needs to be an apulSoft apQualizr2 serial consisting of **APQ2** followed by 5 sections of 4 hexadecimal digits (0-9, A-F).
- If copy/paste was used, try typing manually as copy/paste sometimes copies more than was intended (white spaces, tab stops, etc).
- Check whether you used the correct fields for each entry.

12 Frequently Asked Questions (FAQ)

- **I lost my serial/ID thingy. How can I get it again?**

Just head to <http://www.apulsoft.ch> and use the **Contact apulSoft** link at the bottom. Please add enough information to locate your order in the database and you will receive your serial/ID info as soon as possible.

- **What to do if the window size does not match the GUI size after adjusting the GUI scale?**

Depending on how the host application handles resizing of plugins triggered by the plugin, changing the GUI scale might not immediately work correctly. Any change to the GUI scale is stored in a global preferences file that is read whenever a new instance of apQualizr2 is created. If this problem occurs, first try to just close and reopen the plugin window/editor. If that does not help, set the desired scale on the settings pane and then restart your host application. As long as GUI scale is not changed again, window and content should match.

13 Changelog

- Version 2.0.9
 - Initial public release.
- Version 2.1.0
 - Undo/Redo support.
 - Knobs module added.
 - Improved Installers to work around issues with AAX code signing.
 - Filter and FFT display frequencies always extend to at least 55% of the sample rate.
 - BUGFIX: Sometimes filters accidentally faded in during the first 250 ms of playback.
 - BUGFIX: Various GUI pixel tweaks.
 - BUGFIX: support for switching sample rates not working in some hosts.
- Version 2.1.1
 - Switchable color schemes. Switchable in preferences.
 - Optional Frequency/Gain grid. Switchable in preferences.
 - BUGFIX: Horizontal mouse wheel events did no longer scroll frequencies.
 - BUGFIX: The master gain handle on the main display didn't show modulation correctly.
 - BUGFIX: The Mix module amp factor only worked for integer factors.
 - BUGFIX: One pole low- and highpass filters were producing weird responses for negative gains.